


BOND




6

EASY

INEXPENSIVE

FUN!

**GLAMOUR/GALLER
PINK COTTON (CABLED
PULLOVER)**



GLAMOUR/GALLER PINK COTTON (CABLED PULLOVER)

SIZES: Small, (Medium & Large)

MATERIALS

JOSEPH GALLER'S PARISIEN COTTON #3041, 15 (17, 20) balls, Crochet hook "I".

GAUGE 3

Use Keyplate #3 in stockinette stitch, knit double strand throughout: 4 sts = 1" 11 rows = 2"

SPECIAL INSTRUCTIONS: *When knitting double strands of yarn, place a piece of tape across the front opening (slit) of the yarn guide on the carriage. This helps insure that both strands knit every stitch. Also, watch yarn as it comes from the pull skein or ball to insure that it does not tangle before going into the yarn guide.*

BACK

Bring forward 76 (82, 88) stitches and work 2x1 ribbing (Book 3, Step 3 C & D) for 18 rows. Latch up unworked stitches to complete rib. (NOTE: Ribbing facing you will be on the outside, as sweater is reverse stockinette stitch (Purl side on the outside)). Increase 1 stitch each end next row (Book 3, Step 10). Knit 12 rows even. Work cable using 3 pronged transfer tools (Book 5, Step 5 A-C) 10 (11, 12) stitches in from each end. Make cables in the following manner: Cable is stockinette stitch on a background of reverse stockinette stitch. Drop each stitch of the cable down to the start of the cable (or to where the previous cable-cross was made and latched up). Latch up outside stitches first, then center stitches. Do this every 12 rows, while continuing the cable stitch. Knit until 88 (90, 92) rows above ribbing. Shape armhole by casting off 5 stitches at the beginning of the next 2 rows (Book 3, Step 9). Decrease 1 stitch each end every other row 2 times. With 64 (70, 76) stitches, knit even (continuing with cable) for 44 (46, 48) more rows. Cast off across.

FRONT

Knit the same as the back until 18 (20, 22) rows into the armhole have been completed. Place center 16 (18, 20) stitches on waste yarn (Book 3, Step 2 B). Place all remaining stitches on left hand side of **BOND** on waste yarn and return all those needles to the non-working position. READJUST WEIGHTS BY SLIDING THE RODS IN THE HEM SO THAT THE HEM HANGS EVEN. Working on the right side only, decrease 1 stitch on the neckedge every other row 3 times and the every 4th row 6 times, until 14 (16, 18) stitches remain. Work 2 (4, 6) rows even. Cast off. Replace all stitches on left-hand side to needles (NOT CENTERSTITCHES) and knit as for other side, reversing the shaping on the neckedge.

SLEEVES

Bring 46 (48, 50) needles forward. Work ribbing as for back for 16 rows. Increase 1 stitch each end. Knit increasing 1 stitch each end every 8 (6, 6) rows 10 (11, 12) times, until 68 (72, 76) stitches. Knit 2 (4, 6) rows even. Cast off 5 stitches beginning next 2 rows. Decrease 1 stitch each end every other row 9 times until 40 (44, 48) stitches remain. Cast off 4 stitches beginning next 6 (6, 8) rows until 16 (20, 16) stitches remain. Cast off 6 stitches beginning next 2 rows until 4 (8, 4) stitches remain. Cast off.

FINISHING

Cast off center front stitches now on waste yarn (Book 3, Step 6 A-D). Sew shoulder seams. Make a single crochet edge around neckedge. Sew side seams. Sew sleeve seams and then sew in sleeves.

GAUGE SWATCH

To check the tension knit a swatch at least 6" square. Pull it into shape by pulling down from top and bottom to close up the stitches. Let it rest and then press it. Measure the sts and rows over 4"


If the tension of the yarn you are using is different to the one given in the pattern then knit a size larger or smaller as appropriate. As a general rule, if the tension is 2 sts to 4" more than that given in the pattern then knit as for two sizes larger. But, remember to check the rows to the inch

and make the necessary adjustments to the body and arm lengths to fit you.

If you are not sure what measurement will fit your size, find the actual width of knitting you need for the back. For example, if you are 36" bust then the knitting must be 18" wide plus 2" to allow for ease and seam allowance. If you multiply this by the number of sts to the inch given by your tension swatch, it will give the number of stitches you need to cast on.

KEY PLATE CHART

There are four keyplates. As a guide, use these keyplates with these yarns:



To practice, use a ball of worsted weight with keyplate 3.

DISCLAIMER

The Kimberly Market Corp. has done everything possible to assure the accuracy of these instructions and cannot be responsible for improper working of the Bond by the knitter or for typographical errors.
IMPORTANT: Read books 1 - 4 to assure proper knitting techniques!